Stereolize Shop

Presentation Template Navigation - User Manual

This template is made specifically for touch applications.
It can be used on a touchscreen or via cursor on your computer. But of course you can also use your keyboard to navigate through your presentation.

The template runs in:
Ventuz 3 Professional / Ventuz 3 Express
Version V3.07.00 and higher

The presentation can also run using the FREE Ventuz 3 Express Version.
Just visit www.ventuz.com and download the newest version of Ventuz.
Keep in mind: For the installation of Ventuz 3 to work, you will need Windows 7.

The presentation is best vied in HD resolution (1920x1080).

Opening the Ventuz Project Archive

Start your Ventuz software.
Click “Browse” and select your .vpa download.
Define the location for your Ventuz Project and confirm.
Open the Ventuz scene: StereolizeShop-TEMPLATE-Navigation.vzs.

Control

Press keyboard key “N” for next,
press keyboard key “B” for back,
press keyboard key “R” to reset the presentation.
Note: Your cursor must be in the presentation screen in order for the keyboard keys to work.

Once you’ve opened up the presentation you need to press “N” once to get to the start screen. Then you can start navigating through the presentation by using the buttons.

The end your presentation will automatically jump back to the start screen.

Fonts

To display the right font, please install the font file “AUBREY1_.TTF” on your computer which you will find in the “Fonts” folder in your Ventuz project folder.
Credits: Thanks to Criselda Caecilia Titus for this font.

Slides

You can find all slides in the Project Repository. Simply drag and drop whatever you need into an empty slidemanager slot.
To add or reduce slots, use the green + or – from the slidemanager navigation.

Start Slide

Please note:
If you drag the Start Slide from the Repository to the Slidemanager, you will need to connect the "Next" command of the Slidemanager node to
the exposed "Fired" event otherwise the startbutton will not work. You can find this under the Output tab of the Start Slide Node.

Image Slides

The Image Slides are setup for DDS textures. If you are not able to create DDS you can exchange the image texture node in the Image Slides with a
Texture > Image Loder node with which one you can also open (e.g. jpg).

Inserting your company's logo

Go into the "Start Screen" slide by double clicking and load your logo as DDS texture into the node that is named with " INSERT YOUR LOGO HERE".
If you are not able to create a DDS file you can exchange the node with a Texture > Image Loder node with which one you can also open e.g. jpg.

If you would prefer to see your logo in all slides, you can find a logo dummy in the Slidemanager node itself.
Double click the "TEMPLATE BROWNIE" node and unblock the logo dummy with the keyboard key combination: Strg + B.
And insert your DDS logo same way as in the start screen.

Change the button's colors

To change the color of the Start Screen button go into the Start Screen slide by double clicking on it. Change the color of the "BUTTON COLOR" node.

To change the color of the next and back buttons go into the Slidemanager node.
Double click the "TEMPLATE BROWNIE" node. There you will find two containers "Button NEXT" and "Button BACK".
Inside these containers you will find the "BUTTON COLOR" nodes which will allow you to change to your desired color.

Exporting your Presentation

Once you are ready to present, you can export your presentation via: File > Export > Presentation.vpr. You can now transfer this file to your presentation machine. Double click to start.
Keep in mind: In order to open the presentation *.vpr, Ventuz has to be installed.
If you have chosen special fonts in your presentation, these must be installed on the presentation machine as well.